

VOMS CC API

1.5.0

Generated by Doxygen 1.7.2

Sun Oct 17 2010 19:06:03

Contents

1	Data Structure Index	1
1.1	Data Structures	1
2	File Index	3
2.1	File List	3
3	Data Structure Documentation	5
3.1	attribute Struct Reference	5
3.1.1	Detailed Description	5
3.1.2	Field Documentation	5
3.1.2.1	name	5
3.1.2.2	qualifier	5
3.1.2.3	value	6
3.2	attributelist Struct Reference	6
3.2.1	Detailed Description	6
3.2.2	Field Documentation	6
3.2.2.1	attributes	6
3.2.2.2	grantor	6
3.3	contactdata Struct Reference	6
3.3.1	Detailed Description	7
3.3.2	Field Documentation	7
3.3.2.1	contact	7
3.3.2.2	host	7
3.3.2.3	nick	7
3.3.2.4	port	7
3.3.2.5	version	7
3.3.2.6	vo	8
3.4	data Struct Reference	8
3.4.1	Detailed Description	8
3.4.2	Field Documentation	8
3.4.2.1	cap	8
3.4.2.2	group	8
3.4.2.3	role	9
3.5	voms Struct Reference	9
3.5.1	Detailed Description	10
3.5.2	Constructor & Destructor Documentation	10
3.5.2.1	voms	10
3.5.2.2	voms	10
3.5.2.3	~voms	10

3.5.3	Member Function Documentation	10
3.5.3.1	GetAC	10
3.5.3.2	GetAttributes	10
3.5.3.3	GetTargets	10
3.5.3.4	operator=	10
3.5.4	Friends And Related Function Documentation	10
3.5.4.1	TranslateVOMS	10
3.5.4.2	vomsdata	10
3.5.5	Field Documentation	10
3.5.5.1	custom	10
3.5.5.2	date1	11
3.5.5.3	date2	11
3.5.5.4	fqan	11
3.5.5.5	serial	11
3.5.5.6	server	11
3.5.5.7	serverca	11
3.5.5.8	siglen	11
3.5.5.9	signature	11
3.5.5.10	std	12
3.5.5.11	type	12
3.5.5.12	uri	12
3.5.5.13	user	12
3.5.5.14	userca	12
3.5.5.15	version	12
3.5.5.16	voname	12
3.6	vomsdata Struct Reference	13
3.6.1	Detailed Description	14
3.6.2	Constructor & Destructor Documentation	14
3.6.2.1	vomsdata	14
3.6.2.2	~vomsdata	14
3.6.2.3	vomsdata	14
3.6.3	Member Function Documentation	14
3.6.3.1	AddTarget	14
3.6.3.2	Contact	15
3.6.3.3	Contact	15
3.6.3.4	ContactRaw	15
3.6.3.5	ContactRaw	16
3.6.3.6	DefaultData	16
3.6.3.7	ErrorMessage	16
3.6.3.8	Export	16
3.6.3.9	FindByAlias	17
3.6.3.10	FindByVO	17
3.6.3.11	Import	17
3.6.3.12	ListTargets	17
3.6.3.13	LoadCredentials	18
3.6.3.14	LoadSystemContacts	18
3.6.3.15	LoadUserContacts	18
3.6.3.16	Order	18
3.6.3.17	ResetOrder	18
3.6.3.18	ResetTargets	19

3.6.3.19	Retrieve	19
3.6.3.20	Retrieve	19
3.6.3.21	Retrieve	19
3.6.3.22	RetrieveFromCred	20
3.6.3.23	RetrieveFromCred	20
3.6.3.24	RetrieveFromCtx	20
3.6.3.25	RetrieveFromCtx	20
3.6.3.26	RetrieveFromProxy	21
3.6.3.27	ServerErrors	21
3.6.3.28	SetLifetime	21
3.6.3.29	SetRetryCount	21
3.6.3.30	SetVerificationTime	21
3.6.3.31	SetVerificationType	21
3.6.4	Field Documentation	22
3.6.4.1	data	22
3.6.4.2	error	22
3.6.4.3	extra_data	22
3.6.4.4	workvo	22
4	File Documentation	23
4.1	voms_api.h File Reference	23
4.1.1	Typedef Documentation	24
4.1.1.1	check_sig	24
4.1.2	Enumeration Type Documentation	24
4.1.2.1	data_type	24
4.1.2.2	recurse_type	25
4.1.2.3	verify_type	25
4.1.2.4	verror_type	25
4.1.3	Function Documentation	26
4.1.3.1	getMajorVersionNumber	26
4.1.3.2	getMinorVersionNumber	26
4.1.3.3	getPatchVersionNumber	26

Chapter 1

Data Structure Index

1.1 Data Structures

Here are the data structures with brief descriptions:

attribute	5
attributelist	6
contactdata	6
data (User's characteristics: can be repeated. Generic name-value attribute : can be repeated)	8
voms	9
vomsdata	13

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

voms_api.h	23
------------	-------	----

Chapter 3

Data Structure Documentation

3.1 attribute Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string name
- std::string qualifier
- std::string value

3.1.1 Detailed Description

Definition at line 60 of file voms_api.h.

3.1.2 Field Documentation

3.1.2.1 std::string attribute::name

attribute's group

Definition at line 61 of file voms_api.h.

3.1.2.2 std::string attribute::qualifier

attribute's qualifier

Definition at line 62 of file voms_api.h.

3.1.2.3 std::string attribute::value

attribute's value

Definition at line 63 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.2 attributelist Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [grantor](#)
- std::vector<[attribute](#)> [attributes](#)

3.2.1 Detailed Description

Definition at line 66 of file voms_api.h.

3.2.2 Field Documentation

3.2.2.1 std::vector<[attribute](#)> attributelist::attributes

The attributes themselves.

Definition at line 68 of file voms_api.h.

3.2.2.2 std::string attributelist::grantor

Who granted these attributes.

Definition at line 67 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.3 contactdata Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string `nick`
- std::string `host`
- std::string `contact`
- std::string `vo`
- int `port`
- int `version`

3.3.1 Detailed Description

Definition at line 80 of file voms_api.h.

3.3.2 Field Documentation

3.3.2.1 std::string contactdata::contact

The subject of the server's certificate

Definition at line 86 of file voms_api.h.

3.3.2.2 std::string contactdata::host

The hostname of the server

Definition at line 85 of file voms_api.h.

3.3.2.3 std::string contactdata::nick

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the FindBy* functions. The alias of the server

Definition at line 84 of file voms_api.h.

3.3.2.4 int contactdata::port

The port on which the server is listening

Definition at line 88 of file voms_api.h.

3.3.2.5 int contactdata::version

The version of globus under which the server is running

Definition at line 90 of file voms_api.h.

3.3.2.6 std::string contactdata::vo

The VO served by this server

Definition at line 87 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.4 data Struct Reference

User's characteristics: can be repeated. Generic name-value attribute : can be repeated.

```
#include <voms_api.h>
```

Data Fields

- std::string [group](#)
- std::string [role](#)
- std::string [cap](#)

3.4.1 Detailed Description

User's characteristics: can be repeated. Generic name-value attribute : can be repeated.

Definition at line 52 of file voms_api.h.

3.4.2 Field Documentation

3.4.2.1 std::string data::cap

user's capability

Definition at line 55 of file voms_api.h.

3.4.2.2 std::string data::group

user's group

Definition at line 53 of file voms_api.h.

3.4.2.3 std::string data::role

user's role

Definition at line 54 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.5 voms Struct Reference

```
#include <voms_api.h>
```

Public Member Functions

- [voms \(const voms &\)](#)
- [voms \(\)](#)
- [voms & operator= \(const voms &\)](#)
- [~voms \(\)](#)
- [AC * GetAC \(\)](#)
- [std::vector< attributelist > & GetAttributes \(\)](#)
- [std::vector< std::string > GetTargets \(\)](#)

Data Fields

- int [version](#)
- int [siglen](#)
- std::string [signature](#)
- std::string [user](#)
- std::string [userca](#)
- std::string [server](#)
- std::string [serverca](#)
- std::string [voname](#)
- std::string [uri](#)
- std::string [date1](#)
- std::string [date2](#)
- [data_type type](#)
- std::vector< [data](#) > [std](#)
- std::string [custom](#)
- std::vector< std::string > [fqan](#)
- std::string [serial](#)

Friends

- class [vomsdata](#)
- int [TranslateVOMS](#) (struct vomsdatar *vd, std::vector<[voms](#)> &v, int *error)

3.5.1 Detailed Description

Definition at line 93 of file voms_api.h.

3.5.2 Constructor & Destructor Documentation

[3.5.2.1 voms::voms \(const voms & \)](#)

[3.5.2.2 voms::voms \(\)](#)

[3.5.2.3 voms::~voms \(\)](#)

3.5.3 Member Function Documentation

[3.5.3.1 AC* voms::GetAC \(\)](#)

[3.5.3.2 std::vector<attributelist>& voms::GetAttributes \(\)](#)

Generic attributes

[3.5.3.3 std::vector<std::string> voms::GetTargets \(\)](#)

[3.5.3.4 voms& voms::operator= \(const voms & \)](#)

3.5.4 Friends And Related Function Documentation

[3.5.4.1 int TranslateVOMS \(struct vomsdatar * vd, std::vector<\[voms\]\(#\)> & v, int * error \) \[friend\]](#)

[3.5.4.2 friend class vomsdata \[friend\]](#)

Definition at line 94 of file voms_api.h.

3.5.5 Field Documentation

[3.5.5.1 std::string voms::custom](#)

The data returned by an S command

Definition at line 108 of file voms_api.h.

3.5.5.2 std::string voms::date1

Beginning of validity of the user info

Definition at line 104 of file voms_api.h.

3.5.5.3 std::string voms::date2

End of validity of the user info

Definition at line 105 of file voms_api.h.

3.5.5.4 std::vector<std::string> voms::fqn

Keeps the data in the compact format

Definition at line 110 of file voms_api.h.

3.5.5.5 std::string voms::serial

Serial number. "0" if coming from non-ac

Definition at line 111 of file voms_api.h.

3.5.5.6 std::string voms::server

The VOMS server DN, as from its certificate

Definition at line 100 of file voms_api.h.

3.5.5.7 std::string voms::serverca

The CA which signed the VOMS certificate

Definition at line 101 of file voms_api.h.

3.5.5.8 int voms::siglen

The length of the VOMS server signature

Definition at line 96 of file voms_api.h.

3.5.5.9 std::string voms::signature

The VOMS server signature

Definition at line 97 of file voms_api.h.

3.5.5.10 std::vector<data> voms::std

User's characteristics

Definition at line 107 of file voms_api.h.

3.5.5.11 data_type voms::type

The type of data returned

Definition at line 106 of file voms_api.h.

3.5.5.12 std::string voms::uri

The URI of the VOMS server

Definition at line 103 of file voms_api.h.

3.5.5.13 std::string voms::user

The user's DN, as from his certificate

Definition at line 98 of file voms_api.h.

3.5.5.14 std::string voms::userca

The CA which signed the user's certificate

Definition at line 99 of file voms_api.h.

3.5.5.15 int voms::version

0 means data didn't originate from an AC

Definition at line 95 of file voms_api.h.

3.5.5.16 std::string voms::vuname

The name of the VO to which the VOMS belongs

Definition at line 102 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.6 vomsdata Struct Reference

```
#include <voms_api.h>
```

Data Structures

- class **Initializer**

Public Member Functions

- **vomsdata** (std::string voms_dir="", std::string cert_dir "")
- bool **LoadSystemContacts** (std::string dir "")
- bool **LoadUserContacts** (std::string dir "")
- std::vector< contactdata > **FindByAlias** (std::string alias)
- std::vector< contactdata > **FindByVO** (std::string vo)
- void **Order** (std::string att)
- void **ResetOrder** (void)
- void **AddTarget** (std::string target)
- std::vector< std::string > **ListTargets** (void)
- void **ResetTargets** (void)
- std::string **ServerErrors** (void)
- bool **Retrieve** (X509 *cert, STACK_OF(X509)*chain, recurse_type how=RECURSE_CHAIN)
- bool **Contact** (std::string hostname, int port, std::string servsubject, std::string command)
- bool **Contact** (std::string hostname, int port, std::string servsubject, std::string command, int timeout)
- bool **ContactRaw** (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version)
- bool **ContactRaw** (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version, int timeout)
- void **SetVerificationType** (verify_type how)
- void **SetLifetime** (int lifetime)
- bool **Import** (std::string buffer)
- bool **Export** (std::string &data)
- bool **DefaultData** (voms &)
- std::string **ErrorMessage** (void)
- bool **RetrieveFromCtx** (void *context, recurse_type how)
- bool **RetrieveFromCred** (void *credential, recurse_type how)
- bool **RetrieveFromCtx** (gss_ctx_id_t context, recurse_type how)
- bool **RetrieveFromCred** (gss_cred_id_t credential, recurse_type how)
- bool **Retrieve** (X509_EXTENSION *ext)
- bool **RetrieveFromProxy** (recurse_type how)
- bool **Retrieve** (FILE *file, recurse_type how)
- ~vomsdata ()

- `vomsdata` (`const vomsdata &`)
- `void SetRetryCount` (`int retryCount`)
- `void SetVerificationTime` (`time_t`)
- `bool LoadCredentials` (`X509 *, EVP_PKEY *, STACK_OF(X509)*`)

Data Fields

- `verror_type error`
- `std::vector< voms > data`
- `std::string workvo`
- `std::string extra_data`

3.6.1 Detailed Description

Definition at line 184 of file voms_api.h.

3.6.2 Constructor & Destructor Documentation

3.6.2.1 `vomsdata::vomsdata (std::string voms_dir = "", std::string cert_dir = "")`

Parameters

<code>voms_dir</code>	The directory which contains the certificate of the VOMS server
<code>cert_dir</code>	The directory which contains the certificate of the CA

If `voms_dir` is empty, the value of the environment variable X509_VOMS_DIR is taken.

If `cert_dir` is empty, the value of the environment variable X509_CERT_DIR is taken.

3.6.2.2 `vomsdata::~vomsdata ()`

3.6.2.3 `vomsdata::vomsdata (const vomsdata &)`

3.6.3 Member Function Documentation

3.6.3.1 `void vomsdata::AddTarget (std::string target)`

Adds a target to the AC.

Parameters

<code>target</code>	The target to be added. it should be a FQDN.
---------------------	--

3.6.3.2 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*)

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the --include functionality.

Parameters

<i>hostname</i>	FQDN of the VOMS server
<i>port</i>	the port on which the VOMS server is listening
<i>servsubject</i>	the subject of the server's certificate
<i>command</i>	the command sent to the server

Returns

failure (F) or success (T)

3.6.3.3 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, int *timeout*)

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the --include functionality.

Parameters

<i>hostname</i>	FQDN of the VOMS server
<i>port</i>	the port on which the VOMS server is listening
<i>servsubject</i>	the subject of the server's certificate
<i>command</i>	the command sent to the server

Returns

failure (F) or success (T)

3.6.3.4 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

Parameters

<i>hostname</i>	FQDN of the VOMS server
<i>port</i>	the port on which the VOMS server is listening
<i>servsubject</i>	the subject of the server's certificate
<i>command</i>	the command sent to the server

<i>raw</i>	OUTPUT PARAMETER the answer from the server
<i>version</i>	OUTPUT PARAMETER the version of the answer

Returns

failure (F) or success (T)

3.6.3.5 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*, int *timeout*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

Parameters

<i>hostname</i>	FQDN of the VOMS server
<i>port</i>	the port on which the VOMS server is listening
<i>servsubject</i>	the subject of the server's certificate
<i>command</i>	the command sent to the server
<i>raw</i>	OUTPUT PARAMETER the answer from the server
<i>version</i>	OUTPUT PARAMETER the version of the answer

Returns

failure (F) or success (T)

3.6.3.6 bool vomsdata::DefaultData (voms &)

Get the default data extension from those present in the pseudo certificate

3.6.3.7 std::string vomsdata::ErrorMessage (void)

Gets a textual description of the error.

Returns

A string containing the error message.

3.6.3.8 bool vomsdata::Export (std::string & *data*)

Exports data from [vomsdata::data](#) to the format used for inclusion into a certificate.

The function doesn't verify the data

Parameters

<i>data</i>	The certificate extension
-------------	---------------------------

Returns

Failure (F) or Success (T)

3.6.3.9 std::vector<contactdata> vomsdata::FindByAlias (std::string *alias*)

Finds servers which share a common alias.

Parameters

<i>alias</i>	The alias to look for.
--------------	------------------------

Returns

The servers found. The order in which they are returned is unspecified.

3.6.3.10 std::vector<contactdata> vomsdata::FindByVO (std::string *vo*)

Finds servers which serve a common VO

Parameters

<i>vo</i>	The VO name to look for.
-----------	--------------------------

Returns

The servers found. The order in which they are returned is unspecified.

3.6.3.11 bool vomsdata::Import (std::string *buffer*)

Converts data from the format used for inclusion into a certificate to the internal format

The function does verify the data.

Parameters

<i>buffer</i>	contains the data to be converted
---------------	-----------------------------------

Returns

Failure (F) or Success (T)

3.6.3.12 std::vector<std::string> vomsdata::ListTargets (void)

Returns the list of targets.

3.6.3.13 bool vomsdata::LoadCredentials (X509 *, EVP_PKEY *, STACK_OF(X509)*)

3.6.3.14 bool vomsdata::LoadSystemContacts (std::string dir = "")

Loads the system wide configuration files.

Parameters

<i>dir</i>	The directory in which the files are stored.
------------	--

If *dir* is empty, defaults to /opt/edg/etc/vomses.

Returns

True if all went OK, false otherwise.

3.6.3.15 bool vomsdata::LoadUserContacts (std::string dir = "")

Loads the user-specific configuration files.

Parameters

<i>dir</i>	The directory in which the files are stored.
------------	--

If *dir* is empty, defaults to \$VOMS_USERCONF. If this is empty too, defaults to \$HOME/.edg/vomses, or to ~/.edg/vomses as a last resort.

Returns

True if all went OK, false otherwise.

3.6.3.16 void vomsdata::Order (std::string att)

Sets up the ordering of the results.

Defines the ordering of the data returned by [Contact\(\)](#). Results are ordered in the same order as the calls to this function.

Parameters

<i>att</i>	The attribute to be ordered.
------------	------------------------------

3.6.3.17 void vomsdata::ResetOrder (void)

Resets the ordering.

3.6.3.18 void vomsdata::ResetTargets (void)

Resets the target list.

3.6.3.19 bool vomsdata::Retrieve (X509 * cert, STACK_OF(X509)* chain, recurse_type how = RECURSE_CHAIN)

Extracts the VOMS extension from an X.509 certificate. The function doesn't check the validity of the certificates, but it does check the content of the user data.

Parameters

<i>cert</i>	The certificate with the VOMS extensions
<i>chain</i>	The chain of the validation certificates (only the intermediate ones)
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

3.6.3.20 bool vomsdata::Retrieve (X509_EXTENSION * ext)

Gets VOMS information from the given extension

Parameters

<i>ext</i>	The extension to parse.
------------	-------------------------

Returns

failure (F) or success (T)

3.6.3.21 bool vomsdata::Retrieve (FILE * file, recurse_type how)

Gets VOMS information from a proxy saved as a file.

Parameters

<i>the</i>	file
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

Note: Does NOT verify that the proxy is valid. Such verification must be obtained through other means.

3.6.3.22 bool vomsdata::RetrieveFromCred (void * *credential*, recurse_type *how*)

Gets VOMS information from the given globus credential

Parameters

<i>credential</i>	The credential from which to retrieve the certificate.
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

3.6.3.23 bool vomsdata::RetrieveFromCred (gss_cred_id_t *credential*, recurse_type *how*) [inline]

Gets VOMS information from the given globus credential

Parameters

<i>credential</i>	The credential from which to retrieve the certificate.
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

Definition at line 439 of file voms_api.h.

3.6.3.24 bool vomsdata::RetrieveFromCtx (void * *context*, recurse_type *how*)

Gets VOMS information from the given globus context

Parameters

<i>context</i>	The context from which to retrieve the certificate.
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

3.6.3.25 bool vomsdata::RetrieveFromCtx (gss_ctx_id_t *context*, recurse_type *how*) [inline]

Gets VOMS information from the given globus context

Parameters

<i>context</i>	The context from which to retrieve the certificate.
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

Definition at line 432 of file voms_api.h.

3.6.3.26 bool vomsdata::RetrieveFromProxy (recurse_type *how*)

Gets VOMS information from an existing globus proxy

Parameters

<i>how</i>	Recursion type
------------	----------------

Returns

failure (F) or success (T)

3.6.3.27 std::string vomsdata::ServerErrors (void)

Gets the error message returned by the server

3.6.3.28 void vomsdata::SetLifetime (int *lifetime*)

Set requested lifetime for the [Contact\(\)](#) call.

Parameters

<i>lifetime</i>	Requested lifetime, in seconds
-----------------	--------------------------------

3.6.3.29 void vomsdata::SetRetryCount (int *retryCount*)**3.6.3.30 void vomsdata::SetVerificationTime (time_t)****3.6.3.31 void vomsdata::SetVerificationType (verify_type *how*)**

Sets the type of verification done on the data.

Parameters

<i>how</i>	The type of verification.
------------	---------------------------

3.6.4 Field Documentation

3.6.4.1 std::vector<voms> vomsdata::data

User's info, as in the certificate extension. It may contain data gathered from more than one VOMS server,

Definition at line 358 of file voms_api.h.

3.6.4.2 verror_type vomsdata::error

Error code

Definition at line 203 of file voms_api.h.

3.6.4.3 std::string vomsdata::extra_data

The data specified by the user with the --include switch.

Note that this field doesn't contain the result of a request to the VOMS server, but instead data specified by the user.

The reason for the introduction of this extension is to let a user include important data into his proxy certificate, like, for example, a kerberos ticket

Definition at line 362 of file voms_api.h.

3.6.4.4 std::string vomsdata::workvo

The value of the -vo option of the voms-proxy-init command

Definition at line 361 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

Chapter 4

File Documentation

4.1 voms_api.h File Reference

```
#include <fstream>
#include <string>
#include <vector>
#include "gssapi.h"
#include <openssl/x509.h>
#include <openssl/bio.h>
#include <sys/types.h>
#include "newformat.h"
```

Data Structures

- struct [data](#)
User's characteristics: can be repeated. Generic name-value attribute : can be repeated.
- struct [attribute](#)
- struct [attributelist](#)
- struct [contactdata](#)
- struct [voms](#)
- struct [vomsdata](#)
- class [vomsdata::Initializer](#)

Typedefs

- typedef bool(* [check_sig](#))(X509 *, void *, [verror_type](#) &)

Enumerations

- enum `data_type` { `TYPE_NODATA`, `TYPE_STD`, `TYPE_CUSTOM` }

The type of data returned.

 - enum `reurse_type` { `RECURSE_CHAIN`, `RECURSE_NONE`, `RECURSE_DEEP` }
 - enum `verify_type` {

`VERIFY_FULL` = 0xffffffff, `VERIFY_NONE` = 0x00000000, `VERIFY_DATE` = 0x00000001,
 `VERIFY_TARGET` = 0x00000002,

`VERIFY_KEY` = 0x00000004, `VERIFY_SIGN` = 0x00000008, `VERIFY_ORDER`
= 0x00000010, `VERIFY_ID` = 0x00000020,

`VERIFY_CERTLIST` = 0x00000040 }
 - enum `verror_type` {

`VERR_NONE`, `VERR_NOSOCKET`, `VERR_NOIDENT`, `VERR_COMM`,
 `VERR_PARAM`, `VERR_NOEXT`, `VERR_NOINIT`, `VERR_TIME`,
 `VERR_IDCHECK`, `VERR_EXTRAINFO`, `VERR_FORMAT`, `VERR_NODATA`,
 `VERR_PARSE`, `VERR_DIR`, `VERR_SIGN`, `VERR_SERVER`,
 `VERR_MEM`, `VERR_VERIFY`, `VERR_TYPE`, `VERR_ORDER`,
 `VERR_SERVERCODE`, `VERR_NOTAVAIL`, `VERR_FILE` }
- Error codes.*

Functions

- int `getMajorVersionNumber` (void)
- int `getMinorVersionNumber` (void)
- int `getPatchVersionNumber` (void)

4.1.1 Typedef Documentation

4.1.1.1 `typedef bool(* check_sig)(X509 *, void *, verror_type &)`

Definition at line 182 of file voms_api.h.

4.1.2 Enumeration Type Documentation

4.1.2.1 `enum data_type`

The type of data returned.

Enumerator:

`TYPE_NODATA` no data

TYPE_STD group, role, capability triplet

TYPE_CUSTOM result of an S command

Definition at line 74 of file voms_api.h.

4.1.2.2 enum recurse_type

Enumerator:

RECURSE_CHAIN

RECURSE_NONE

RECURSE_DEEP

Definition at line 135 of file voms_api.h.

4.1.2.3 enum verify_type

Enumerator:

VERIFY_FULL

VERIFY_NONE

VERIFY_DATE

VERIFY_TARGET

VERIFY_KEY

VERIFY_SIGN

VERIFY_ORDER

VERIFY_ID

VERIFY_CERTLIST

Definition at line 141 of file voms_api.h.

4.1.2.4 enum verror_type

Error codes.

Enumerator:

VERR_NONE

VERR_NOSOCKET Socket problem

VERR_NOIDENT Cannot identify itself (certificate problem)

VERR_COMM Server problem

VERR_PARAM Wrong parameters

VERR_NOEXT VOMS extension missing

VERR_NOINIT Initialization error
VERR_TIME Error in time checking
VERR_IDCHECK User data in extension different from the real ones
VERR_EXTRAINFO VO name and URI missing
VERR_FORMAT Wrong data format
VERR_NODATA Empty extension
VERR_PARSE Parse error
VERR_DIR Directory error
VERR_SIGN Signature error
VERR_SERVER Unidentifiable VOMS server
VERR_MEM Memory problems
VERR_VERIFY Generic verification error
VERR_TYPE Returned data of unknown type
VERR_ORDER Ordering different than required
VERR_SERVERCODE Error message from the server
VERR_NOTAVAIL Method not available
VERR_FILE Error reading data from file

Definition at line 155 of file voms_api.h.

4.1.3 Function Documentation

4.1.3.1 `int getMajorVersionNumber(void)`

4.1.3.2 `int getMinorVersionNumber(void)`

4.1.3.3 `int getPatchVersionNumber(void)`

Index

~voms
 voms, 10
~vomsdata
 vomsdata, 14

AddTarget
 vomsdata, 14

attribute, 5
 name, 5
 qualifier, 5
 value, 5

attributelist, 6
 attributes, 6
 grantor, 6

attributes
 attributelist, 6

cap
 data, 8

check_sig
 voms_api.h, 24

Contact
 vomsdata, 14, 15

contact
 contactdata, 7

contactdata, 6
 contact, 7
 host, 7
 nick, 7
 port, 7
 version, 7
 vo, 7

ContactRaw
 vomsdata, 15, 16

custom
 voms, 10

data, 8
 cap, 8
 group, 8
 role, 8

 vomsdata, 22
data_type
 voms_api.h, 24

date1
 voms, 10

date2
 voms, 11

DefaultData
 vomsdata, 16

error
 vomsdata, 22

ErrorMessage
 vomsdata, 16

Export
 vomsdata, 16

extra_data
 vomsdata, 22

FindByAlias
 vomsdata, 17

FindByVO
 vomsdata, 17

fqan
 voms, 11

GetAC
 voms, 10

GetAttributes
 voms, 10

getMajorVersionNumber
 voms_api.h, 26

getMinorVersionNumber
 voms_api.h, 26

getPatchVersionNumber
 voms_api.h, 26

GetTargets
 voms, 10

grantor
 attributelist, 6

group

```

        data, 8
host
    contactdata, 7
Import
    vomsdata, 17
ListTargets
    vomsdata, 17
LoadCredentials
    vomsdata, 17
LoadSystemContacts
    vomsdata, 18
LoadUserContacts
    vomsdata, 18
name
    attribute, 5
nick
    contactdata, 7
operator=
    voms, 10
Order
    vomsdata, 18
port
    contactdata, 7
qualifier
    attribute, 5
RECURSE_CHAIN
    voms_api.h, 25
RECURSE_DEEP
    voms_api.h, 25
RECURSE_NONE
    voms_api.h, 25
recurse_type
    voms_api.h, 25
ResetOrder
    vomsdata, 18
ResetTargets
    vomsdata, 18
Retrieve
    vomsdata, 19
RetrieveFromCred
    vomsdata, 19, 20
RetrieveFromCtx
    vomsdata, 20
        RetrieveFromProxy
            vomsdata, 21
        role
            data, 8
        serial
            voms, 11
        server
            voms, 11
        serverca
            voms, 11
    ServerErrors
        vomsdata, 21
    SetLifetime
        vomsdata, 21
    SetRetryCount
        vomsdata, 21
    SetVerificationTime
        vomsdata, 21
    SetVerificationType
        vomsdata, 21
    siglen
        voms, 11
    signature
        voms, 11
    std
        voms, 11
TranslateVOMS
    voms, 10
type
    voms, 12
TYPE_CUSTOM
    voms_api.h, 25
TYPE_NODATA
    voms_api.h, 24
TYPE_STD
    voms_api.h, 24
uri
    voms, 12
user
    voms, 12
userca
    voms, 12
value
    attribute, 5
VERIFY_CERTLIST
    voms_api.h, 25

```

VERIFY_DATE
 voms_api.h, 25
VERIFY_FULL
 voms_api.h, 25
VERIFY_ID
 voms_api.h, 25
VERIFY_KEY
 voms_api.h, 25
VERIFY_NONE
 voms_api.h, 25
VERIFY_ORDER
 voms_api.h, 25
VERIFY_SIGN
 voms_api.h, 25
VERIFY_TARGET
 voms_api.h, 25
verify_type
 voms_api.h, 25
VERR_COMM
 voms_api.h, 25
VERR_DIR
 voms_api.h, 26
VERR_EXTRAINFO
 voms_api.h, 26
VERR_FILE
 voms_api.h, 26
VERR_FORMAT
 voms_api.h, 26
VERR_IDCHECK
 voms_api.h, 26
VERR_MEM
 voms_api.h, 26
VERR_NODATA
 voms_api.h, 26
VERR_NOEXT
 voms_api.h, 25
VERR_NOIDENT
 voms_api.h, 25
VERR_NOINIT
 voms_api.h, 25
VERR_NONE
 voms_api.h, 25
VERR_NOSOCKET
 voms_api.h, 25
VERR_NOTAVAIL
 voms_api.h, 26
VERR_ORDER
 voms_api.h, 26
VERR_PARAM
 voms_api.h, 25

VERR_PARSE
 voms_api.h, 26
VERR_SERVER
 voms_api.h, 26
VERR_SERVERCODE
 voms_api.h, 26
VERR_SIGN
 voms_api.h, 26
VERR_TIME
 voms_api.h, 26
VERR_TYPE
 voms_api.h, 26
VERR_VERIFY
 voms_api.h, 26
verror_type
 voms_api.h, 25
version
 contactdata, 7
 voms, 12
vo
 contactdata, 7
voms, 9
 ~voms, 10
 custom, 10
 date1, 10
 date2, 11
 fqan, 11
 GetAC, 10
 GetAttributes, 10
 GetTargets, 10
 operator=, 10
 serial, 11
 server, 11
 serverca, 11
 siglen, 11
 signature, 11
 std, 11
 TranslateVOMS, 10
 type, 12
 uri, 12
 user, 12
 userca, 12
 version, 12
 voms, 10
 vomsdata, 10
 voname, 12
 voms_api.h
 RECURSE_CHAIN, 25
 RECURSE_DEEP, 25
 RECURSE_NONE, 25

TYPE_CUSTOM, 25
TYPE_NODATA, 24
TYPE_STD, 24
VERIFY_CERTLIST, 25
VERIFY_DATE, 25
VERIFY_FULL, 25
VERIFY_ID, 25
VERIFY_KEY, 25
VERIFY_NONE, 25
VERIFY_ORDER, 25
VERIFY_SIGN, 25
VERIFY_TARGET, 25
VERR_COMM, 25
VERR_DIR, 26
VERR_EXTRAINFO, 26
VERR_FILE, 26
VERR_FORMAT, 26
VERR_IDCHECK, 26
VERR_MEM, 26
VERR_NODATA, 26
VERR_NOEXT, 25
VERR_NOIDENT, 25
VERR_NOINIT, 25
VERR_NONE, 25
VERR_NOSOCKET, 25
VERR_NOTAVAIL, 26
VERR_ORDER, 26
VERR_PARAM, 25
VERR_PARSE, 26
VERR_SERVER, 26
VERR_SERVERCODE, 26
VERR_SIGN, 26
VERR_TIME, 26
VERR_TYPE, 26
VERR_VERIFY, 26
voms_api.h, 23
check_sig, 24
data_type, 24
getMajorVersionNumber, 26
getMinorVersionNumber, 26
getPatchVersionNumber, 26
recurse_type, 25
verify_type, 25
verror_type, 25
vomsdata, 13
~vomsdata, 14
AddTarget, 14
Contact, 14, 15
ContactRaw, 15, 16
data, 22
DefaultData, 16
error, 22
ErrorMessage, 16
Export, 16
extra_data, 22
FindByAlias, 17
FindByVO, 17
Import, 17
ListTargets, 17
LoadCredentials, 17
LoadSystemContacts, 18
LoadUserContacts, 18
Order, 18
ResetOrder, 18
ResetTargets, 18
Retrieve, 19
RetrieveFromCred, 19, 20
RetrieveFromCtx, 20
RetrieveFromProxy, 21
ServerErrors, 21
SetLifetime, 21
SetRetryCount, 21
SetVerificationTime, 21
SetVerificationType, 21
voms, 10
vomsdata, 14
workvo, 22
voname
voms, 12
workvo
vomsdata, 22